Ankle Warmers Crochet Pattern

Free crochet pattern · adult · mardingezituru.com

Crochet ankle warmers are short tubes that keep the gap between your jeans and your shoes warm. These have ribbed bands at the top and bottom so they stay up, and an open mesh middle that is light and quick to work. They are made in joined rounds, so there is no seam.

Each one is about 10 in / 26 cm around and 9 in / 23 cm tall; the ribbing stretches to fit most adult ankles.



The ankle warmers in dusty blue worsted yarn.

Pattern at a glance

- **Skill level:** easy (dc in joined rounds, post stitches, chain spaces)
- **Size:** adult, 10 in / 26 cm around before stretching, 9 in / 23 cm tall
- **Yarn:** worsted (aran / 4) acrylic, about 108 yd / 99 m for the pair
- **Hook:** 5 mm (US H/8)
- **Gauge:** 14 dc x 7 rounds = 4 in / 10 cm
- **Time:** about 2 hours for the pair

Abbreviations (US terms)

• **ch** chain · **sk** skip · **sl st** slip stitch · **dc** double crochet · **fpdc / bpdc** front / back post double crochet · **ch-1 sp** the space under a ch 1

Before you start

- Every round starts with ch 2 (it does not count) and ends with a sl st to the first stitch.
- In the mesh rounds each dc goes into the ch-1 space of the round below, so the holes stack in neat columns.

The pattern

Ankle Warmer (make 2)

Color: start with A (dusty blue).

Ch 36 and join. Rounds 2 to 4 and 14 to 16 are the ribbed bands.

- [ ] **Rnd 1:** Dc around. (36)
- [ ] **Rnds 2–4:** (fpdc, bpdc) ×18. (36)
- [ ] **Rnd 5:** (dc, ch 1, sk 1) ×18. (36)
- [ ] **Rnds 6–12:** (ch 1, sk 1, dc in next ch-1 sp) ×18. (36)
- [ ] **Rnd 13:** Dc around. (36)
- [ ] **Rnds 14–16:** (fpdc, bpdc) ×18. (36)

Finish: Ch 36 and join into a ring without twisting; FO after R16.



Worn over sneakers with rolled-up jeans.

Tips

- **Taller leg warmers:** work more mesh rounds; each round adds about 0.6 in / 1.5 cm.
- **Boot cuffs:** make them with 4 rib rounds at the top and fold the top band over the edge of your boots.
- **Solid instead of mesh:** work dc in every stitch in rounds 5 to 12.

FAQ

Do they slide down?

The ribbing holds them. If they are still loose, work the bottom band with a hook one size smaller.

Can I wear them for dance or yoga?

Yes. In cotton they are lighter and less warm; acrylic is warmer for outdoors.

Matching makes: the crochet socks and the chunky slippers.